




- Turn on the tablet and connect to WiFi
- Place your finger firmly on the camera at the top of the tablet and then slowly drag your finger down to about an inch below the camera and hold there for 10 seconds (white dot in the second image for reference on finger placement).
- This will trigger a pop-up that requires a code.




- Enter the code 69914891 and then press Enter. (If this code does not work, please try 548278537 or 983845623)










- Select "launch browser" from the list of debugging tools and then select 'Allow All' on each pop-up that appears on the screen.
  - Note: none of these functions are used by your tablet, but the browser will not open without them.



- Go to [bit.ly/agent-soul](https://bit.ly/agent-soul)
- Select Update OTA Software



<ul style="list-style-type: none"> <li>● Download and open the available file by clicking on it. <ul style="list-style-type: none"> <li>○ If you are directed to accept from an unknown source, you can click settings to allow from the source, then hit the back arrow and it will prompt you to install the update.</li> </ul> </li> </ul>	
<ul style="list-style-type: none"> <li>● Select Install</li> </ul>	
<ul style="list-style-type: none"> <li>● Select Done on the bottom right corner.</li> </ul>	
<ul style="list-style-type: none"> <li>● Select the back arrow at the bottom of the screen. This should take you back to the browser where you should enter <b>https://bit.ly/com-soul</b></li> </ul>	
<ul style="list-style-type: none"> <li>● Select Update Commercial Software</li> </ul>	
<ul style="list-style-type: none"> <li>● This will bring you to a download screen.</li> </ul>	
<ul style="list-style-type: none"> <li>● Wait until you hear a chime from the</li> </ul>	

<p>tablet then select the icon that says "bike-RELEASE"</p> <ul style="list-style-type: none"><li>● Select Install</li></ul>	
<ul style="list-style-type: none"><li>● The tablet is now updated with the latest version of commercial software and you will be able to successfully complete onboarding.</li></ul>	